


Programmer's Manual

TiePie Dll's



for: TP112
TP208
TP508
TP801 AWG ISA
TP801 AWG PCI
TE6100
TiePieSCOPE HS508
TiePieSCOPE HS801 AWG
Handyprobe HP2
Handyscope HS2
Handyscope HS3 AWG

Revision 1.15

Table of contents

Table of contents	1
How can I...	5
Perform my first measurement	5
Understand the error codes	6
Error codes	6
Defined constants	6
Open / Close the instrument	7
Search and Initialize the Instrument	7
Close the Instrument	7
Get information about my instrument	8
Get the calibration date	8
Get the instrument serial number	8
Determine the available input sensitivities	9
Determine the available input resolutions	9
Get the maximum sampling frequency	10
Get the maximum record length	10
Check for availability of DC hardware offset adjustment	10
Check for a square wave generator	11
Check for a function generator	11
Get the maximum amplitude of the function generator	11
Perform a measurement	12
Start the measurement	12
Retrieve the data	13
Get all measurement data in Volts	13
Get one sample of the measurement data, in Volts	13
Get all measurement data, binary	14
Get one sample of the measurement data, binary	14
Get all digital input values	15
Get one sample of the digital input values	15
Advanced measurement routines	16
Start a measurement	16
Check if the hardware is measuring	16
Abort a running measurement	17
Read the trigger status	17
Read the measurement status	17

Force a trigger	18
Retrieve the measured data in binary format	18
Retrieve the measured data in Volts	19
Get the data from a specific channel in binary format . . .	20
Get the date from a specific channel in Volts	20
Example of use of the routines	21
Streaming measurements	22
Setting the receiver handle	22
Determine the message identifiers	23
Setting up streaming measurements	25
Getting the current transfer mode	26
Performing streaming measurements	26
Using callback functions	27
Controlling the input resolution	28
Set the input resolution	28
Get the current input resolution	28
Control which channels are measured	29
Get the current measure mode	29
Set the measure mode	29
Control the time base	30
Get the current record length	30
Set the record length	30
Get the current number of post samples	31
Set the number of post samples	31
Get the current sampling frequency	32
Set the sampling frequency	32
Get the sample clock status	33
Set the sample clock status	33
Control the analog input channels	34
Get the current input sensitivity	34
Set the input sensitivity	34
Get the current auto ranging status	35
Set the auto ranging status	35
Get the current input coupling	36
Set the input coupling	36
Get the current DC level value	37
Set the DC level value	37
Control the trigger system	38
Get the current trigger source	38
Set the trigger source	38

Get the current trigger mode	39
Set the trigger mode	39
Get the current trigger level	40
Set the trigger level	40
Get the current trigger hysteresis	41
Set the trigger hysteresis	41
Select the PXI external trigger signals	42
Get the current used PXI external trigger signals	42
Set the PXI external trigger slopes	43
Get the current PXI external trigger slopes	43
Get the current trigger timeout value	44
Set the trigger timeout value	44
Control the digital outputs	45
Set the digital outputs	45
Get the current status of the digital outputs	45
Control the Square Wave generator	46
Get the current square wave generator frequency	46
Set the square wave generator frequency	46
Control the Arbitrary Waveform Generator	47
Set the generator signal type	47
Get the current generator signal type	47
Set the generator amplitude	48
Get the current generator amplitude	48
Set the generator DC Offset	49
Get the current generator DC Offset	49
Set the generator signal symmetry	50
Get the current generator signal symmetry	50
Set the generator frequency	51
Get the current generator frequency	52
Set the generator trigger source	53
Get the current generator trigger source	53
Fill the function generator waveform memory	54
Set the generator output state	55
Get the current generator output state	55
Generate bursts	56
Resistance measurements	57
Setup resistance measurements	57
Retrieve the resistance values	57

Perform my first measurement

Before performing a measurement, the instrument must first be initialized, using the routine `InitInstrument`. If this routine returns a non-zero value the initialization has failed and it is not possible to perform any measurements.

After initializing the hardware you can:

- modify the measurement settings
- start a measurement

These two actions can be executed in any order and as often as required.

Finally the routine `ExitInstrument` has to be called to deactivate the instrument and free any used resources.

Example in Pascal code:

```
const E_NO_ERRORS = 0;

if InitInstrument = E_NO_ERRORS then      {initialize instrument}
begin                                   {and allocate resources}
    while MeasureMore do
    begin
        if ChangeSettings then
        begin
            OldFreq := GetFrequency;      {query a setting}
            SetFrequency((OldFreq* 10)-1000 ); {change a setting}
        end; { if }
        if StartMeasurement = E_NO_ERRORS then {measure}
        begin
            for Sample := 0 to GetRecordLengh do
            begin                               {retrieve data}
                GetOneMeasurement(Data1[Sample], Data2[Sample]);
            end; { for }
        end; { if }
    end; { while }
    ExitInstrument;                            { free resources}
end
else
begin
    writeln( 'Error: No hardware found...' );
end; { else }
```

Legend:

- bold** = reserved words
- 123 = number
- italic* = comment

Understand the error codes

Error codes

Code Names	Code Values	
	Hexadecimal	Binairry
E_INVALID_VALUE	= 0x0020 ;	/*0000000000100000*/
E_INVALID_CHANNEL	= 0x0010 ;	/*0000000000010000*/
E_NO_GENERATOR	= 0x0008 ;	/*0000000000001000*/
E_NOT_SUPPORTED	= 0x0004 ;	/*0000000000000100*/
E_NOT_INITIALIZED	= 0x0002 ;	/*0000000000000010*/
E_NO_HARDWARE	= 0x0001 ;	/*0000000000000001*/
E_NO_ERRORS	= 0x0000 ;	/*0000000000000000*/

Defined constants

For several programming environments declaration files (header files) are available. These files contain declarations for all the available functions in the DLL, but also declarations of many used constants, like for trigger sources.

It is recommended that the constants from these declaration files are used in the application that uses the DLL. When in a future release of the DLL some values have changed, they will be adapted in the declaration file as well, so the application only needs to be recompiled, it will not affect the rest of the program.

Search and Initialize the Instrument

`word InitInstrument (word wAddress);`

Descriptions: Initialize the hardware of the instrument. Set default measurement settings, allocate memory and obtain the calibration constants etc.

Parallel port connected instruments, USB instruments and PCI bus instruments detect the hardware by themselves and ignore the address parameters.

Input: **wAddress** The hardware address of the instrument should be passed to this routine.

Output: **Returnvalue** E_NO_ERRORS;
 E_NO_HARDWARE

Note All instruments have their calibration constants in internal, non-volatile memory, except for the TP208 and TP508. These have to be calibrated using internal routines. This is done automatically at first startup everyday. Some relays will begin to click.

Close the Instrument

`word ExitInstrument (void);`

Description: Close the instrument. Free any allocated resources and memory, place the relays in their passive state, etc.

Input: -

Output: **Returnvalue** E_NO_ERRORS;
 E_NOT_INITIALIZED

Get information about my instrument

Get the calibration date

word GetCalibrationDate (dword *dwDate);

Description: This routine returns the calibration date of the instrument.
The date is encoded in a packed 32 bit variable:

```
31 30 29 28 27 26 25 24 23 22 21 20 19 18 17 16 15 14 13 12 11 10 9 8 7 6 5 4 3 2 1 0
|<----->|<----->|<----->|<----->|
|   day (8 bits)   |   (month (8 bits)   |   year (16 bits)   |   |
```

Example decoding routine in C/C++:

```
day   = number >> 24;           /* highest 8 bits */
month = (number >> 16) & 0xFF;  /* middle 8 bits */
year  = number & 0xFFFF;       /* lowest 16 bits */
```

Input: -

Output: dwDate The calibration date

Returnvalue E_NO_ERRORS

E_NOT_SUPPORTED

E_NO_HARDWARE

Get the instrument serial number

word GetSerialNumber (dword *dwSerialNumber);

Description: This routine returns the Serial Number of the instrument.
This number is hardcoded in the hardware. TP112, TP208
and TP508 do not have a serial number in the instrument.

Input: -

Output: dwSerialNumber the serial number

Returnvalue E_NO_ERRORS

E_NOT_SUPPORTED

E_NO_HARDWARE

Determine the available input sensitivities

word GetAvailableSensitivities(double *dSensitivities);

description: This routine retrieves the available input sensitivities from the hardware and stores them in an array.

dSensitivities is an 20 elements large array. The caller must ensure that there is enough space in the arrays to contain the data. Therefor both the arrays must be at least

20 * sizeof(double)

At return, all elements containing a non-zero value, contain an input sensitivity. This is a full scale value. So if an element contains the value 4.0, the input sensitivity is 4 Volt full scale, enabling to measure input signals from -4 Volt - +4 Volt.

input:

-

output:

dSensitivities Return address for the array of input sensitivities

Returnvalue E_NO_ERRORS
E_NO_HARDWARE

Determine the available input resolutions

word GetAvailableResolutions(double *dResolutions);

description: The Handyscope HS3 supports different, user selectable input resolutions. This routine retrieves the available input resolutions from the hardware and stores them in an array.

dResolutions is an 20 elements large array. The caller must ensure that there is enough space in the arrays to contain the data. Therefor both the arrays must be at least

20 * sizeof(double)

At return, all elements containing a non-zero value, contain an input resolution in number of bits.

input:

-

output:

dResolutions Return address for the array of input sensitivities

Returnvalue E_NO_ERRORS
E_NO_HARDWARE

Get the maximum sampling frequency

dword GetMaxSampleFrequency(void);

Description: The different instruments have different maximum sampling frequencies. This routine queries the maximum sampling frequency.

Input: -

Output: **Returnvalue** The maximum sampling frequency the instrument supports in Hz.

Get the maximum record length

dword GetMaxRecordLength(void);

Description: The different instruments have different record lengths. This routine queries the maximum available record length per channel, in samples.

Input: -

Output: **Returnvalue** The maximum record length the instrument supports in number of samples.

Check for availability of DC hardware offset adjustment

word GetDCLevelStatus(void);

Description: Some instruments support DC Hardware offset adjustment. This routine checks if the DC Level is supported.

Input: -

Output: **Returnvalue** E_NO_ERRORS
E_NOT_SUPPORTED
E_NO_HARDWARE

Check for a square wave generator

word GetSquareWaveGenStatus(void);

Description: Some instruments have a built-in square wave generator, the HS508 for example. This routine checks the presence of the generator.

Input:

-

Output:

Returnvalue E_NO_ERRORS
E_NO_GENERATOR
E_NO_HARDWARE

Check for a function generator

word GetFunctionGenStatus(void);

Description: The TiePieSCOPE HS801, TP801 and Handyscope HS3 can have a built-in arbitrary waveform generator. When this function returns E_NO_GENERATOR, the HS801, TP801 or Handyscope HS3 is equipped with a simple square wave generator.

Input:

-

Output:

Returnvalue E_NO_ERRORS
E_NO_GENERATOR
E_NO_HARDWARE

Get the maximum amplitude of the function generator

word GetFuncGenMaxAmplitude(double *dAmplitude);

Description: The maximum output voltage for the TiePieSCOPE HS801 and Handyscope HS3 generator is 12 Volt, the maximum output voltage for the TP801 generator is 10 Volt. This routine determines the maximum voltage.

Input:

-

Output:

dAmplitude The maximum amplitude the generator supports.
Returnvalue E_NO_ERRORS
E_NO_GENERATOR
E_NO_HARDWARE

Start the measurement

word StartMeasurement (void);

Description: This routine tells the hardware to perform a single measurement. The measurement is initiated, and then the routine will wait until the hardware is ready. When the hardware is ready, the measured data is transferred from the hardware acquisition memory into the computer memory, inside the DLL.

Input:

-

Output:

Returnvalue E_NO_ERRORS
E_NOT_INITIALIZED
E_NO_HARDWARE

Remark:

Perform a measurement. One (software) measurement equals a `record_length` number of hardware-measurements. So the hardware will fill it's internal buffer. This routine will wait until the hardware is done.

Get all measurement data in Volts

word GetMeasurement (double *dCh1, double *dCh2);

Description: This routine transfers the measured data from the acquisition memory in the DLL into the memory in the application. For each sample, the value in Volts is calculated.

dCh1 and dCh2 are both array. The caller must ensure that there is enough space in the arrays to contain the data. Therefore both the arrays must be at least

RecordLength * sizeof(double)

Input:

-

Output:

dCh1 The array to which the data of channel 1 should be passed.

dCh2 The array to which the data of channel 2 should be passed.

Returnvalue E_NO_ERRORS
 E_NO_HARDWARE

Get one sample of the measurement data, in Volts

word GetOneMeasurement (dword wIndex, double *dCh1, double *dCh2);

Description: This routine transfers a single sample per channel from the acquisition memory in the DLL into the memory of the application. The value in Volts is calculated for each sample.

Input: wIndex The index of the measured data point.

Output: dCh1 Return address for the measured data from channel 1.

dCh2 Return address for the measured data from channel 2.

Returnvalue E_NO_ERRORS
 E_NO_HARDWARE

Get all measurement data, binary

word GetMeasurementRaw (word *wCh1, word *wCh2);

Description: This routine transfers the measured data from the acquisition memory in the DLL into the memory in the application. The measured data is returned in binary values. A value of 0 corresponds to -Sensitivity, 32767 corresponds to 0 and 65535 to +Sensitivity in Volts. wCh1 and wCh2 are arrays. The caller must ensure that there is enough space in the arrays to contain the data. Therefore the arrays must be at least
RecordLength * sizeof(word)

Input:

-

Output:

wCh1 The array to which the measured data of channel 1 should be passed.

wCh2 The array to which the measured data of channel 2 should be passed.

Returnvalue E_NO_ERRORS
 E_NO_HARDWARE

Get one sample of the measurement data, binary

word GetOneMeasurementRaw(dword wIndex, word *wCh1, word *wCh2);

Description: This routine transfers a single sample per channel from the acquisition memory in the DLL to the memory of the application. The measured data is returned in binary values. A value of 0 corresponds to -Sensitivity, 32767 corresponds to 0 and 65535 to +Sensitivity in Volts.

Input: wIndex The index of the measured data point

Output: wCh1 Return address for the measured data from channel 1

wCh2 Return address for the measured data from channel 2

Returnvalue E_NO_ERRORS
 E_NO_HARDWARE

Get all digital input values

word GetDigitalInputValues(word *wValues);

Description: The TP112 has eight digital inputs, which are sampled simultaneously with the analog input channels.

This routine transfers the measured digital values from the memory in the DLL into the memory in the application. The measured data is returned in binary values. Each bit in the digital data words represents a digital input. wValues is an array. The caller must ensure that there is enough space in the array to contain the data. Therefore the array must be at least

RecordLength * sizeof(word)

Input:

-

Output:

Returnvalue E_NO_ERRORS
E_NOT_SUPPORTED
E_NO_HARDWARE

Get one sample of the digital input values

word GetOneDigitalValue(word wIndex; word *wValue);

Description: This routine transfers a single digital input value from the memory in the DLL to the memory of the application.

Input:

wIndex The index of the measured data point, relative to the trigger point (negative for pre samples, positive for post samples)

Output:

wValue Return address for the digital input value.

Returnvalue E_NO_ERRORS
E_NOT_SUPPORTED
E_NO_HARDWARE

Advanced measurement routines

The previously mentioned routine `StartMeasurement` takes care of a complete measurement. It sets up the hardware to perform a measurement and then starts the hardware measurement. Then it will wait for the measurement to be ready. In the mean while, it checks the triggered flag of the hardware and checks if a trigger time out has occurred. If that has happened, it will force a trigger. Then it will wait for the measurement to be ready. When the measurement is ready, the measured data will be transferred from the hardware to memory inside the DLL. While doing that, it will check if auto range is required. When all data is transferred and checked, the routine will end.

The application can then transfer the data from the DLL memory to it's own memory and process it.

For certain applications it might be usefull to split up this process into individual steps. The following routines enable this. When these routines are used, no Trigger timeout is available.

Start a measurement

`word ADC_Start;`

Description: This routine writes any new instrument setting information to the hardware and then starts the measurement. If the hardware is already measuring, this measurement is aborted. Previous measured data is lost

Input: -

Output: **Returnvalue** `E_NOT_INITIALIZED`
 `E_NO_ERRORS`
 `E_NO_HARDWARE`

Check if the hardware is measuring

`word ADC_Running;`

Description: This routine checks if the hardware is currently measuring

Input: -

Output: **Returnvalue** `0` = not measuring
 `1` = measuring

Abort a running measurement

word ADC_Abort;

Description: This routine aborts a running measurement. Any measured data is lost. It is not required to abort a running measurement before starting a new one, StartMeasurement does this already.

Input: -

Output: **Returnvalue** E_NOT_INITIALIZED
 E_NO_ERRORS
 E_NO_HARDWARE

Read the trigger status

word ADC_Triggered;

Description: This routine reads the trigger status from the hardware.

Input: -

Output: **Returnvalue** 0 = not triggered
 1 = Ch1 caused trigger
 2 = Ch2 caused trigger
 4 = External input caused trigger

Remark: Returnvalue can be a combination of indicated values.

Read the measurement status

word ADC_Ready;

Description: This routine checks if the measurement is ready or not.

Input: -

Output: **Returnvalue** 0 = not ready
 1 = ready

Force a trigger

word ADC_ForceTrig;

Description: This routine forces a trigger when the input signal will not meet the trigger specifications. This allows to do a measurement and see the signal.

Input: -

Output: Returnvalue E_NOT_INITIALIZED
E_NO_ERRORS
E_NO_HARDWARE

Retrieve the measured data in binary format

word ADC_GetData(word *wCh1, word *wCh2);

Description: This routine transfers the measured data from the acquisition memory in the hardware via the dll into the memory in the application. The measured data is returned in binary values. A value of 0 corresponds to -Sensitivity, 32767 corresponds to 0 and 65535 to +Sensitivity in Volts. wCh1 and wCh2 are arrays. The caller must ensure that there is enough space in the arrays to contain the data. Therefore the arrays must be at least

RecordLength * sizeof(word)

Input: -

Output: wCh1 The array to which the measured data of channel 1 should be passed.
wCh2 The array to which the measured data of channel 2 should be passed.
Returnvalue E_NO_ERRORS
E_NO_HARDWARE

Retrieve the measured data in Volts

```
word ADC_GetDataVolt( double *dCh1, double *Ch2 );
```

Description: This routine transfers the measured data from the acquisition memory in the hardware via the dll into the memory in the application. The measured data is returned in volt. dCh1 and dCh2 are arrays. The caller must ensure that there is enough space in the arrays to contain the data. Therefor the arrays must be at least

`RecordLength * sizeof(double)`

Input:

-

Output:

dCh1 The array to which the measured data of channel 1 should be passed.

dCh2 The array to which the measured data of channel 2 should be passed.

Returnvalue E_NO_ERRORS
 E_NO_HARDWARE

Get the data from a specific channel in binary format

word ADC_GetDataCh(word wCh, word *wData);

Description: This routine transfers the measured data of one channel from the acquisition memory in the hardware via the dll into the memory in the application. The measured data is returned in binary values. A value of 0 corresponds to -Sensitivity, 32767 corresponds to 0 and 65535 to +Sensitivity in Volts. wData is an array. The caller must ensure that there is enough space in the array to contain the data. Therefore the array must be at least

RecordLength * sizeof(word)

Input: wCh Indicates from which channel the data has to be retrieved

Output: wData The array to which the measured data of the requested channel should be passed.

Returnvalue E_NO_ERRORS
 E_NO_HARDWARE

Get the data from a specific channel in Volts

word ADC_GetDataVoltCh(word wCh, double *Data);

Description: This routine transfers the measured data of one channel from the acquisition memory in the hardware via the dll into the memory in the application. The measured data is returned in volt. dData is an array. The caller must ensure that there is enough space in the array to contain the data. Therefore the array must be at least

RecordLength * sizeof(double)

Input: wCh Indicates from which channel the data has to be retrieved

Output: dData The array to which the measured data of the requested channel should be passed.

Returnvalue E_NO_ERRORS
 E_NO_HARDWARE

Example of use of the routines

To use the advanced measurement routines, your application could look like the following:

```
.  
.
ADC_Start;
while bContinue do
begin
    if ADC_Ready = 1 then
    begin
        ADC_Getdata( @Ch1WordArray, @Ch2WordArray );
        ADC_Start;
        ApplicationProcessData;
    end; { if }
.
.
```

Streaming measurements

It is possible to do streaming measurements with the Handyscope HS3. Each time a new sample is measured, it will be transferred to the computer and is available to be processed.

This way of measuring uses the Windows message system to let the application know new samples are available. This requires some additional facilities in the application that will use the Handyscope HS3.

First of all, the Handyscope HS3 needs to know the Window Handle (unique identifier) of the application or object that will receive the Handyscope HS3 events.

Setting the receiver handle

word SetReceiverHandle(HWND Handle);

Description: This routine tells the instrument which Window handle is its receiver. This is required to send messages through the windows message system.

Input: **Handle** The handle of the window that will receive the instrument events.

Output: **Returnvalue** E_NO_ERRORS
 E_NO_HARDWARE
 E_INVALID_VALUE

Next step is to let the application know which messages will be sent by the instrument to inform the application about the measurement that's going on. The instrument can send two different messages. Each message has a unique identifier, which are requested from windows, by the instrument. The application will have to ask the instrument what the identifiers of the messages are.

The messages are:

DLLTransUpdate	This message is sent by the DLL each time when a new sample is available
DLLTransReady	This message is sent by the DLL when the complete streaming measurement is ready

Determine the message identifiers

word GetMessageID(dword dwMessage, dword *dwIdentifier);

Description: This routine asks the identifier for a specific message that will be sent by the instrument

Input: **dwMessage** identifies the message of which the identifier is requested. Possible values are:

DLLTransUpdate (1)

DLLTransReady (2)

Output: **dwIdentifier** the identifier of the requested message

Returnvalue E_NO_ERRORS

E_NO_HARDWARE

E_INVALID_VALUE

Now the identifiers are known, a message receiving routine will have to be made in the application. It should receive windows messages that are sent to the application and it should respond to the two specific messages and pass all other messages on to their normal receiver.

The owner of this message receiver should have the same handle as that is set using SetReceiverHandle().

How this message receiving routine will look, depends completely on the programming environment / language that is used to create the application. An example in Delphi Pascal is given below:

```

const DLLTransUpDate = 1;
      DLLTransReady  = 2;

var    WM_TRANS_UPDATE : HWND;
      WM_TRANS_READY  : HWND;

type TForm1 = class( TForm )
.
.
private
  procedure WndProc( var Message : TMessage ); override;
.
end; { TForm1 }

procedure TForm1.SetMessageIDs;
begin
  if SetOwnerHandle( Handle ) = E_NO_ERRORS then
    begin
      GetMessageID( DLLTransUpDate, @WM_TRANS_UPDATE );
      GetMessageID( DLLTransReady,  @WM_TRANS_READY );
    end; { if }
end; { TForm1.SetMessageIDs }

procedure TForm1.WndProc( var Message : TMessage );
begin
  if Message.Msg = WM_TRANS_UPDATE then
    begin
      HandleTransUpDate;
    end { if }
  else if Message.Msg = WM_TRANS_READY then
    begin
      HandleTransReady;
    end { else if }
  else
    begin
      { *
       * handle this message in the normal way
       *}
      inherited;
    end; { else }
end; { TForm1.WndProc }

```

Each message calls its own message handler.

The message handler **HandleTransUpdate()** should retrieve the measured data from the DLL. This can be done using the one of the before mentioned routines, like e.g. **ADC_GetData()**. After the data is retrieved, it can be processed (e.g. drawn in a graph).

The message handler **HandleTransReady()** will tell the application that the measurement is ready. It could e.g. initiate a save to disk action, or update the user interface.

Setting up streaming measurements

To tell the instrument a streaming measurement has to be performed, following routine has to be used.

word SetTransferMode(dword dwMode);

Description: This routine tells the instrument what kind of measurement has to be performed.

Input: **dwMode** determines the requested data transfer mode. Possible values are:

tmBlock (0) default value. During the measurement, all data is stored in the instrument. When the measurement is ready, all data is transferred in one block to the computer. This is normal oscilloscope mode

tmStream (1) Each time during the measurement that new data is available, it will be transferred to the computer. So a measurement gives a constant stream of data.

Output: **Returnvalue** **E_NO_ERRORS**
 E_NO_HARDWARE
 E_INVALID_VALUE

Getting the current transfer mode

word GetTransferMode(dword *dwMode);

Description: This routine reads the current set transfer mode from the instrument.

Input: -

Output: **dwMode** holds the current data transfer mode.

Returnvalue E_NO_ERRORS

E_NO_HARDWARE

Performing streaming measurements

When the receiver handle of the DLL is set properly, the message identifiers have been determined, the message handlers have been created and the transfer mode is set to streaming mode, streaming measurements can be performed.

The sampling speed and the record length have to be set to the required values and the input channels have to be set to appropriate values (auto ranging does not work in streaming mode). There is no trigger and no pre- or post trigger available in streaming mode.

A streaming measurement is started with the before mentioned routine **ADC_Start()**. During the measurement messages will be sent each time a new sample is measured. These can be used to update the screen of the application and show the measured data.

When the measurement is ready the corresponding message is sent and the application can do what is required.

To stop a running measurement, call **ADC_Abort()**. This will stop the running measurement. When the measurement is stopped, the DLLTransReady message is sent.

Using callback functions

Instead of using the messages, it is also possible to use callback functions. When there is new data available or the current measurement is finished, a message will be sent, as described before, but also a function in the application can be called. The DLL has two function pointers which have to be set to these functions.

word SetTransUpdateCallback(TAVLTransUpdate pAddress)

<i>description</i>	This routine sets the pointer for the Update function, which will be called each time new data is available.
<i>input:</i>	pAddress a pointer to a function with the following prototype: void TransUpdate(dword Counter) The parameter Counter will hold the index number of the last read sample.
<i>output</i>	return value E_NO_HARDWARE E_INVALID_VALUE E_NO_ERRORS

word SetTransReadyCallback(TAVLTransReady pAddress)

<i>description</i>	This routine sets the pointer for the Ready function, which will be called when the total measurement is ready.
<i>input:</i>	pAddress a pointer to a function with the following prototype: void TransUpdate(void)
<i>output</i>	return value E_NO_HARDWARE E_INVALID_VALUE E_NO_ERRORS

Controlling the input resolution

The Handyscope HS3 supports a number of different input resolutions.

Set the input resolution

word SetResolution(byte byResolution);

Description: This routine sets the input resolution of the hardware.
Use GetAvailableResolutions() to determine which resolutions are available.

Input: **byResolution** the new resolution, in bits

Output: **Returnvalue** E_NO_ERRORS
 E_INVALID_VALUE
 E_NOT_SUPPORTED
 E_NO_HARDWARE

Remark: When setting a new input resolution, the maximum sampling frequency of the hardware changes as well.
 Use GetMaxSampleFrequency() to determine the new maximum sampling frequency.

Get the current input resolution

word GetResolution (byte *byResolution);

Description: This routine retrieves the currently set input resolution in bits.

Input: -

Output: **byResolution** the return address for the resolution
 Returnvalue E_NO_ERRORS
 E_NO_HARDWARE

Get the current measure mode

word GetMeasureMode(byte *byMode);

Description: This routine returns the current Measure Mode:

- 1 : Ch1 the signal at channel 1 is measured
- 2 : Ch2 the signal at channel 2 is measured
- 3 : Ch1 + Ch2 the signals at channel 1 and 2 are measured simultaneously

Input: -

Output: byMode The return address for the Measure Mode.

Returnvalue E_NO_ERRORS
 E_INVALID_VALUE
 E_NO_HARDWARE

Set the measure mode

word SetMeasureMode(byte byMode);

Description: This routine changes the Measure Mode, see also `GetMeasureMode`.

Input: byMode The new measure mode (1, 2 or 3).

Output: Returnvalue E_NO_ERRORS
 E_INVALID_VALUE
 E_NO_HARDWARE

Get the current record length

`dword GetRecordLength(void);`

Description: This routine returns the total number of points to be digitized. The number of pre samples (number of samples to measure **before** the trigger occurred) is calculated like this:
`PreSamples = RecordLength - PostSamples.`

Input: -

Output: **Returnvalue** The total number of points to be digitized per channel.

Set the record length

`word SetRecordLength(dword wTotal);`

Description: This routine sets the total number of points to be digitized. The maximum record length can be determined with the routine `GetMaxRecordLength()`. The minimum is 0.

Input: **wTotal** The total number of points to be digitized per channel.

Output: **Returnvalue** E_NO_ERRORS
E_INVALID_VALUE
E_NO_HARDWARE

Remark: Setting a record length smaller than the number of post samples gives an E_INVALID_VALUE error

Get the current number of post samples

dword GetPostSamples(void);

Description: This routine returns the number of post samples to measure (the number of samples **after** the trigger has occurred).

Input: -

Output: **Returnvalue** The current selected number of post samples to measure.

Set the number of post samples

word SetPostSamples(dword wPost);

Description: This routine sets the number of post samples. This number must be between 0 and the record length.

Input: **wPost** The requested number of post samples to measure.

Output: **Returnvalue** E_NO_ERRORS
 E_INVALID_VALUE
 E_NO_HARDWARE

Remark: Setting a number of post samples larger than the record length gives an E_INVALID_VALUE error

Get the current sampling frequency

dword GetSampleFrequency(void);

Description: This routine returns the current set sampling frequency in Hz. The minimum/maximum frequency supported is instrument dependent.

Input: -

Output: Returnvalue The current sampling frequency in Hz.

Set the sampling frequency

word SetSampleFrequency(dword *dFreq);

Remarks: The routine sets the sampling frequency. The hardware is not capable of creating every selected frequency so the hardware chooses the nearest allowed frequency to use, this is the frequency that is returned in dFreq.

Input: dFreq The requested sampling frequency in Hz

Output: dFreq The actual selected sampling frequency in Hz.

Returnvalue E_NO_ERRORS

E_NO_HARDWARE

Get the sample clock status

word GetExternalClock(word *wMode);

Description: This routine determines whether the sampling clock uses the internal Crystal oscillator or the external clock input
Only 50 MHz devices support external clock input

Input:

-

Output:

wMode The status of the internal clock,
 0 = clock internal
 1 = clock external

Returnvalue E_NO_ERRORS
 E_NOT_SUPPORTED
 E_NO_HARDWARE

Set the sample clock status

word SetExternalClock(word wMode);

Description: This routine sets the sampling clock mode: is te internal crystal oscillator used or the external clock input?
Only 50 MHz devices support external clock input

Input:

wMode 0 = internal clock
 1 = external clock

Output:

Returnvalue E_NO_ERRORS
 E_INVALID_VALUE
 E_NOT_SUPPORTED
 E_NO_HARDWARE

Get the current input sensitivity

word GetSensitivity (byte byCh, double *dSens);

Description: This routine returns the current selected full scale input sensitivity in Volts for the selected channel.

Input: **byCh** The channel whose current Sensitivity is requested (1, 2)

Output: **dSens** The return address for the sensitivity.

Returnvalue E_NO_ERRORS
 E_INVALID_CHANNEL
 E_NO_HARDWARE

Set the input sensitivity

word SetSensitivity(byte byCh, double *dSens);

Description: This routine sets the Sensitivity for the selected channel. The hardware can only deal with a limited number of ranges. The sensitivity that matches the entered sensitivity best is used. This is the value that will be returned in dSens.

Input: **byCh** The channel whose Sensitivity is to be changed (1, 2)

dSens The new Sensitivity in Volts

Output: **dSens** Contains the actual set Sensitivity, on return

Returnvalue E_NO_ERRORS
 E_INVALID_CHANNEL
 E_NO_HARDWARE

Get the current auto ranging status

word GetAutoRanging(byte byCh, byte *byMode);

Description: This routine returns the current autoranging mode:

0 : autoranging is off

1 : autoranging is on.

If autoranging is on then for a channel the sensitivity will be automatically adjusted if the input signal becomes too large or too small.

When a measurement is performed, the data is examined. If that data indicates another range will provide better results, the hardware is set to a new sensitivity. The **next** measurement that is performed, will be using that new sensitivity. Autoranging has no effect on a current measurement.

Input: byCh The channel whose current Autoranging mode is requested (1, 2).

Output: byMode Return address for the Autoranging mode.

Returnvalue E_NO_ERRORS
 E_INVALID_CHANNEL
 E_NO_HARDWARE

Set the auto ranging status

word SetAutoRanging(byte byCh, byte byMode);

Description: This routine selects the autoranging mode:

0 : turn Autoranging off

1 : turn Autoranging on.

See also **GetAutoRanging**.

Input: byCh The channel whose Autoranging mode has to be set (1, 2).

byMode The new value for the Autoranging mode.

Output: Returnvalue E_NO_ERRORS
 E_INVALID_CHANNEL
 E_INVALID_VALUE
 E_NO_HARDWARE

Get the current input coupling

word GetCoupling(byte byCh, byte *byMode);

Description: This routine returns the current signal coupling for the selected channel:

0 : coupling AC

1 : coupling DC.

In DC mode both the DC and the AC components of the signal are measured.

In AC mode only the AC component is measured.

Input: **byCh** The channel whose current coupling is requested (1, 2)

Output: **byMode** Return address for the current coupling.

Returnvalue E_NO_ERRORS
 E_INVALID_CHANNEL
 E_INVALID_VALUE
 E_NO_HARDWARE

Set the input coupling

word SetCoupling(byte byCh, byte byMode);

Description: This routine changes the signal coupling for the selected channel. See also **GetCoupling**.

Input: **byCh** The channel whose Coupling is to be changed (1, 2).

byMode The new coupling for the selected channel (0 or 1).

Output: **Returnvalue** E_NO_ERRORS
 E_INVALID_CHANNEL
 E_INVALID_VALUE
 E_NO_HARDWARE

Get the current DC level value

word GetDcLevel(byte byCh, double *dLevel);

Description: This routine returns the current DC Level value for the selected channel. This voltage is added to the input signal before digitizing. This is used to shift a signal that is outside the current input range into the input range.

Input: **byCh** The channel whose DC Level is requested (1, 2)

Output: **dLevel** Return address for the current DC Level.

Returnvalue E_NO_ERRORS
 E_INVALID_CHANNEL
 E_NOT_SUPPORTED
 E_NO_HARDWARE

Set the DC level value

word SetDcLevel(byte byCh, double dLevel);

Description: This routine is used to change the DC Level for the selected channel. The DC Level has a minimum of $-2 \times \text{sensitivity}$ and a maximum of $+2 \times \text{sensitivity}$. If the sensitivity changes, the DC level is automatically checked and clipped if necessary. See also *GetDcLevel*.

Input: **byCh** The channel whose DC Level is to be set (1, 2)

dLevel The new DC Level in Volts

Output: **Returnvalue** E_NO_ERRORS
 E_INVALID_CHANNEL
 E_INVALID_VALUE
 E_NOT_SUPPORTED
 E_NO_HARDWARE

Control the trigger system

Get the current trigger source

word GetTriggerSource(byte *bySource);

Description: This routine is used to retrieve the current Trigger Source.

0 :	Ch1Trig	Channel 1
1 :	Ch2Trig	Channel 2
2 :	Ch3Trig	Channel 3
3 :	Ch4Trig	Channel 4
4 :	ExtTrig	a digital external signal
5 :	AnaExt	an analog external signal
6 :	AndTrig	Channel 1 AND Channel 2
7 :	OrTrig	Channel 1 OR Channel 2
8 :	XorTrig	Channel 1 XOR Channel 2
9 :	NoTrig	no source, measure immediately
10 :	not used	
11 :	PxiExtTrig	PXI bus digital trigger signals
12 :	GenStart	start of the Handyscope HS3 generator
13 :	GenStop	stop of the Handyscope HS3 generator
14 :	GenNew	each new period of the HS3 generator

Input: -

Output: bySource The current trigger source.
Returnvalue E_NO_ERRORS, E_INVALID_VALUE
E_NO_HARDWARE

Set the trigger source

word SetTriggerSource(byte bySource);

Description: This routine sets the trigger source.

Input: bySource The new trigger source.

Output: Returnvalue E_NO_ERRORS, E_INVALID_VALUE
E_NOT_SUPPORTED
E_NO_HARDWARE

Note Not all devices support all Trigger Sources. If the Trigger Source is not supported, the error value **E_NOT_SUPPORTED** is returned.

Get the current trigger mode

word GetTriggerMode(byte *byMode);

Description: This routine is used to query the current Trigger Mode.

0	Rising	trigger on rising slope
1	Falling	trigger on falling slope
2	InWindow	trigger when signal gets inside window
3	OutWindow	trigger when signal gets outside window
4	TVLine	trigger on TV line sync pulse
5	TVFieldOdd	trigger on TV odd frame sync pulse
6	TVFieldEven	trigger on TV even frame sync pulse

Input:

-

Output: byMode The current trigger mode.

Returnvalue E_NO_ERRORS
E_INVALID_VALUE
E_NO_HARDWARE

Set the trigger mode

word SetTriggerMode(byte byMode);

Description: This routine is used to set the Trigger Mode. See also **GetTriggerSource**. Some trigger modes are not available on all instruments, in that case, the value E_NOT_SUPPORTED will be returned.

Input: byMode The new trigger mode.

Output: Returnvalue E_NO_ERRORS
E_INVALID_VALUE
E_NOT_SUPPORTED
E_NO_HARDWARE

Get the current trigger level

word GetTriggerLevel(byte byCh, double *dLevel);

Description: This routine is used to retrieve the Trigger Level of the selected channel. The hardware starts to measure when the signal passes this level. The routine SetTriggerMode can be used to select the trigger slope.

Input: byCh The channel whose Trigger Level is to be retrieved (1 or 2).

Output: dLevel Return address for the Trigger Level.

Returnvalue E_NO_ERRORS
 E_INVALID_CHANNEL
 E_NO_HARDWARE

Set the trigger level

word SetTriggerLevel(byte byCh, double dLevel);

Description: This routine is used to set the Trigger Level. The Trigger Level is valid if it is between -sensitivity and +sensitivity.

Input: byCh The channel whose Trigger Level is to be set (1 or 2).

 dLevel The new Trigger Level in Volts.

Output: Returnvalue E_NO_ERRORS
 E_INVALID_CHANNEL
 E_INVALID_VALUE
 E_NO_HARDWARE

Note The Trigger Level applies only to analog trigger sources, not to digital trigger sources.

Get the current trigger hysteresis

word GetTriggerHys(byte byCh; double *dHysteresis);

Description: This routine is used to retrieve the current Trigger Hysteresis. The hysteresis is the minimum voltage change that is required to comply with the trigger conditions. This is used to minimize the influence of the noise on a signal on the trigger system.

Input: **byCh** The channel whose Trigger Hysteresis is to be retrieved (1 or 2).

Output: **dHysteresis** Return address for the Trigger Hysteresis.
 Returnvalue E_NO_ERROR
 E_INVALID_CHANNEL
 E_NO_HARDWARE

Set the trigger hysteresis

word SetTriggerHys(byte byCh; double dHysteresis);

Description: This routine changes the hysteresis, see also **GetTriggerHys**.

Input: **byCh** The channel whose Trigger Hysteresis is to be set (1 or 2).

dHysteresis The new trigger hysteresis.
Output: **Returnvalue** E_NO_ERRORS
 E_INVALID_VALUE
 E_INVALID_CHANNEL
 E_NO_HARDWARE

Upper and lower limits of the hysteresis:

Slope	Lower limit	Upper limit
rising	0	level + sens
falling	0	sens - level

Note The Trigger Hysteresis applies only to analog trigger sources, not to digital trigger sources.

The TE6100 has 8 digital external trigger inputs, at the PXI bus, which can be used to trigger the measurement. It is possible to select which inputs have to be used and if the inputs have to respond to a rising or a falling slope.

Select the PXI external trigger signals

word SetPXITriggerEnables(byte byEnables);

Description: This routine determines which of the eight PXI external trigger inputs have to be used. When more than one input is selected, trigger occurs when one or more inputs become active (logic OR). Which input state is active, is determined by the Slopes setting, see next page.

Input: **byEnables** a bit pattern that defines which inputs have to be used. Bit 0 represents input 0, bit 1 represents input 1 etc.
When a bit is high, the corresponding input is used.
When a bit is low, the corresponding input is not used.

Output: **Returnvalue** E_NO_ERRORS,
E_NOT_SUPPORTED
E_NO_HARDWARE

Get the current used PXI external trigger signals

word GetPXITriggerEnables(byte *byEnables);

Description: This routine retrieves the currently selected PXI external trigger inputs.

Input: -

Output: **byEnables** a bit pattern that defines which inputs are currently used. See also the routine SetPXITriggerEnables

Returnvalue: E_NO_ERRORS
E_NOT_SUPPORTED
E_NO_HARDWARE

Set the PXI external trigger slopes

word SetPXITriggerSlopes(byte bySlopes);

Description: This routine determines for each PXI external trigger input individually whether it should respond to a falling or a rising slope.

Input: **bySlopes** a bit pattern that defines how the slope settings for each input is set.
Each bit represents an input, bit 0 represents input 0, bit 1 represents input 1 etc.
When a bit is high, the corresponding input responds to a rising slope.
When a bit is low, the corresponding input responds to a falling slope.

Output: **ReturnValue** E_NO_ERRORS
E_NOT_SUPPORTED
E_NO_HARDWARE

Get the current PXI external trigger slopes

word GetPXITriggerSlopes(byte *bySlopes);

Description: This routines determines how the slope sensitivities for the PXI external trigger inputs are set.

Input: -

Output: **bySlopes** a bit pattern that defines how the slope settings for each input is set.
Each bit represents an input, bit 0 represents input 0, bit 1 represents input 1 etc.
When a bit is high, the corresponding input responds to a rising slope.
When a bit is low, the corresponding input responds to a falling slope.

Returnvalue E_NO_ERRORS
E_NOT_SUPPORTED
E_NO_HARDWARE

Get the current trigger timeout value

`dword GetTriggerTimeOut(void);`

Description: This routine is used to query the current Timeout value. When this Timeout period has elapsed and the hardware has not seen a trigger, then a trigger is forced so that the hardware can start to measure. This way it is possible to measure a signal that has not met the trigger conditions.

Input: -

Output: **Returnvalue** The current Timeout value in msec.

Set the trigger timeout value

`dword SetTriggerTimeOut(dword ITimeout);`

Description: This routine sets the Timeout value, see also `GetTimeOut`.

Input: **ITimeout** The new timeout value in msec.

Output: **Returnvalue** E_NO_ERRORS
E_NO_HARDWARE

Set the digital outputs

```
word SetDigitalOutputs( byte byValue );
```

Description: The TP112 is equipped with 8 digital outputs, which can be set individually.

This routine sets the status of the digital outputs.

Input: **byValue** the new status of the outputs. Each bit represents an output.

Output: **Returnvalue** E_NO_ERRORS
 E_NOT_SUPPORTED
 E_NO_HARDWARE

Get the current status of the digital outputs

```
word GetDigitalOutputs( byte *byValue );
```

Description: This routine gets the current status of the digital outputs.

Input: -

Output: **byValue** the status of the outputs. Each bit represents an output.

Returnvalue E_NO_ERRORS
 E_NOT_SUPPORTED
 E_NO_HARDWARE

Get the current square wave generator frequency

`double GetSquareWaveGenFrequency(void);`

Description: Some instruments have a built-in generator, the HS508 for example. This routine returns the generator frequency in Hz.

Input: -

Output: **Returnvalue** The generator frequency in Hz.

Remarks: Not all instruments have a square wave generator, use the routine `GetSquareWaveGenStatus()` to check if a square wave generator is available

Set the square wave generator frequency

`word SetSquareWaveGenFrequency(double *dFreq);`

Remarks: The routine sets the frequency. The hardware is not capable of using every frequency so the hardware chooses the nearest legal frequency to use, this is the frequency that is returned in `dFreq`. See also `GetGeneratorFrequency`.

Input: **dFreq** the requested frequency in Hz.
A value "zero" switches the output off

Output: **dFreq** the frequency that is actually made.

Returnvalue `E_NO_ERRORS`
`E_NO_GENERATOR`
`E_NO_HARDWARE`

Remarks: Not all instruments have a square wave generator, use `GetSquareWaveGenStatus()` to check if a square wave generator is available

Set the generator signal type

word SetFuncGenSignalType(word wSignalType);

Description: This routine sets the signal type of the function generator.

Input: **wSignalType** The requested signal type

- 0 Sine wave
- 1 Triangular wave
- 2 Square wave
- 3 DC
- 4 Noise
- 5 Arbitrary signal

Output: **Returnvalue:** E_NO_ERRORS
 E_NO_GENERATOR
 E_INVALID_VALUE
 E_NO_HARDWARE

Remark: When **Arbitrary** is selected, the contents of the function generator memory will be "played" continuously. This memory is used for every signal type, so each time when selecting **Arbitrary**, use the function **FillFuncGenMemory()** to fill the memory with the requested signal.

Get the current generator signal type

word GetFuncGenSignalType(word *wSignalType);

Description: This routine returns the currently selected signal type.

Input: -

Output: **wSignalType** The currently selected signal type
 See **SetFuncGenSignalType** for possible
 values for wSignalType

Returnvalue E_NO_ERRORS
 E_NO_GENERATOR
 E_INVALID_VALUE
 E_NO_HARDWARE

Set the generator amplitude

```
word SetFuncGenAmplitude( double dAmplitude );
```

Description: This routine sets the output amplitude of the function generator in volts. When the requested amplitude is smaller than zero or larger than the maximum supported amplitude, E_INVALID_VALUE is returned and the requested value is ignored.

When signal type DC is selected, the absolute amplitude of the signal is determined by the amplitude and the polarity is determined through the **DC offset**.

Input: dAmplitude the function generator amplitude in Volts:
0 <= value <= MaxAmplitude

```
Output:      Returnvalue      E_NO_ERRORS
                                E_NO_GENERATOR
                                E_INVALID_VALUE
                                E_NO_HARDWARE
```

Get the current generator amplitude

```
word GetFuncGenAmplitude( double *dAmplitude );
```

Description: This routine determines the currently selected amplitude of the function generator

Input: -

Output: dAmplitude the function generator amplitude in Volts:
0 <= value <= MaxAmplitude

```

Returnvalue  E_NO_ERRORS
             E_NO_GENERATOR
             E_INVALID_VALUE
             E_NO_HARDWARE

```

Set the generator DC Offset

```
word SetFuncGenDCOffset( double dDCOffset );
```

Description: This routine applies a DC offset to the output signal. The value is entered in Volts.

When signal type **DC** is selected, the DC offset value is used to determine the polarity of the output signal. A value ≥ 0 Volt results in a positive output signal, a value < 0 Volt results in a negative output signal. The amplitude of the DC signal is determined through the Amplitude value.

Input: dDCOffset the requested offset in Volts:
-MaxAmpl <= value <= +MaxAmpl

<i>Output:</i>	Returnvalue	E_NO_ERRORS
		E_NO_GENERATOR
		E_INVALID_VALUE
		E_NO_HARDWARE

Get the current generator DC Offset

```
word GetFuncGenDCOffset( double *dDCOffset );
```

Description: This routine determines the currently selected DC offset value of the function generator

Input: -

Output: dDCOffset the currently selected DC Offset value

Returnvalue E_NO_ERRORS
 E_NO_GENERATOR
 E_INVALID_VALUE
 E_NO_HARDWARE

Set the generator signal symmetry

word SetFuncGenSymmetry(double dSymmetry);

Description: This routine sets the symmetry of the output signal. The symmetry can be set between 0 and 100. With a symmetry of 50, the positive part of the output signal and negative part of the output signal are equally long. With a symmetry of 25, the positive part of the output signal takes 25% of the total period and the negative part takes 75% of the total period. With signal types **DC**, **Noise** and **Arbitrary**, the symmetry value is ignored.

Input: **dSymmetry** The requested symmetry value:
 0 <= value <= 100

Output: **Returnvalue** E_NO_ERRORS
 E_NO_GENERATOR
 E_INVALID_VALUE
 E_NO_HARDWARE

Get the current generator signal symmetry

word GetFuncGenSymmetry(double *dSymmetry);

Description: This routine retrieves the currently selected symmetry of the output signal.

Input: -

Output: **dSymmetry** the current symmetry value

Returnvalue E_NO_ERRORS
 E_NO_GENERATOR
 E_INVALID_VALUE
 E_NO_HARDWARE

Set the generator frequency

```
word SetFuncGenFrequency( double *dFrequency );
```

Description: When signal type Sine, Triangular, Square or Noise is selected (DDS mode), this routine sets the frequency of the output signal of the function generator.

When signal type **Arbitrary** is selected, the frequency settings behaves slightly different. When 1024 samples are loaded into the waveform memory (DDS mode), this routine sets the frequency of the output signal. When more samples are loaded into the waveform memory (linear mode), this routine sets the frequency of the sampling clock of the function generator. Only a limited number of frequencies are available.

Input: dFrequency DDS mode: the requested frequency of the
 output signal:

0.001 <= dFrequency <= 2,000,000

Linear mode: the requested frequency of the sampling clock in 15 steps:

38.1,	610,	2441,
9765,	39062,	78125,
156250,	321500,	625000,
1250000,	2500000,	5000000,
10000000,	25000000,	50000000

Output: **dFrequency** the hardware can not support any arbitrary frequency within the available range. The value that was actually selected is returned.

Returnvalue

- E_NO_ERRORS
- E_NO_GENERATOR
- E_INVALID_VALUE
- E_NO_HARDWARE

Get the current generator frequency

word GetFuncGenFrequency(double *dFrequency);

Description: This routine determines the currently set frequency.

Input: -

Output:

dFrequency	The currently set frequency in Hz
Returnvalue	E_NO_ERRORS
	E_NO_GENERATOR
	E_INVALID_VALUE
	E_NO_HARDWARE

Set the generator trigger source

word SetFuncGenTrigSource(byte bySource);

Description: The Handyscope HS3 function generator can set to be started by an external trigger signal.

This routine sets the function generator trigger source:

4 : tsExtTrig a digital external signal

9 : tsNoTrig no source, generate immediately

The default value is NoTrig

Input: bySource the requested trigger source:

Output: Returnvalue E_NO_ERRORS
E_INVALID_VALUE
E_NOT_SUPPORTED
E_NO_HARDWARE

Get the current generator trigger source

word SetFuncGenTrigSource(byte *bySource);

Description: This routine determines the currently selected function generator trigger source

Input: -

Output: wSource the currently selected trigger source

Returnvalue E_NO_ERRORS
E_INVALID_VALUE
E_NOT_SUPPORTED
E_NO_HARDWARE

Fill the function generator waveform memory

word FillFuncGenMemory(dword wNrPoints; word *wFuncGenData);

description: This routine fills the function generator waveform memory with user defined data.

The generator can operate in two different modes: DDS and Linear. When operating in DDS mode, 1024 samples must be loaded. These 1024 samples will form one period of the output signal. When operating in Linear mode, the maximum record length samples (depends on the instrument, e.g. 65536 or 131072) must be loaded. These samples will form one period of the output signal.

The data must be in unsigned 16 bits values. A value of 32767 produces a 0 Volt signal, 65535 results in positive full output scale and a value of 0 results in negative full output scale.

The amplitude parameter of the function generator determines the exact value of full scale. If an amplitude of 8 Volt is selected, full scale will be 8 Volt.

Input: **dNrPoints** the number of waveform points that must be loaded: 1024 or 65536 or 131072. Also determines whether the function generator operates in DDS or Linear mode.

wFuncGenData an array of 1024, 65536 or 131072 unsigned 16 bits values, containing the signal that must be loaded. The caller must ensure that enough data is allocated.

Output: **Returnvalue** E_NO_ERRORS
 E_NO_GENERATOR
 E_INVALID_VALUE
 E_NO_HARDWARE

Remark: When generating a predefined signal, like e.g. a sinewave, the memory is filled with a sine wave pattern and the generator operates in DDS mode. So each time one selects signal type Arbitrary, the memory has to be filled again with the user defined pattern.

Set the generator output state

word SetFuncGenOutputOn(word wValue);

Description: This routine switches the output of the function generator on or off.

<i>Input:</i>	wValue	The new output state
		0 output is off
		1 output is on
<i>Output:</i>	Returnvalue	E_NO_ERRORS
		E_NO_GENERATOR
		E_INVALID_VALUE
		E_NO_HARDWARE

Get the current generator output state

word GetFuncGenOutputOn(word *wValue);

Description: This routine determines the current setting of the function generator output

<i>Input:</i>	-	
<i>Output:</i>	*wValue	The current setting of the output
		0 output is off
		1 output is on
	Returnvalue	E_NO_ERRORS
		E_NO_GENERATOR
		E_INVALID_VALUE
		E_NO_HARDWARE

Generate bursts

```
word FuncGenBurst( word wNrPeriods );
```

Description: This routine will make the Handyscope HS3 generator generate a burst with a requested number of periods of the selected signal. When the burst is finished, the output will remain at the last generated amplitude value.

Input: **wNrPeriods** the requested number of periods to generate.

Any value > 0 will switch on burst mode.

The value 0 will switch off burst mode and start continuous generation again.

```
Output:  Returnvalue  E_NO_ERRORS
          E_NOT_SUPPORTED
          E_NO_HARDWARE
```

Resistance measurements

Some instruments have special hardware to perform resistance measurements.

Setup resistance measurements

word SetupOhmMeasurements(word wMode);

Description: This routine sets the instrument up to perform resistance measurements. Several properties of the instrument are adapted: input sensitivity, signal coupling, record length, sampling frequency, autoranging, trigger source, trigger timeout, acquisition mode. These are all brought to the required state and should not to be set to other values afterwards.

<i>Input:</i>	wMode	0	switch resistance measurements off
		1	switch resistance measurements on
<i>Output:</i>	returnvalue	E_NO_ERRORS	
		E_INVALID_VALUE	
		E_NOT_SUPPORTED	
		E_NO_HARDWARE	

Retrieve the resistance values

After resistance measurements are switched on, and a measurement is performed in the normal way, the resistance values can be retrieved by using the function

word GetOhmValues(double *dValue1; double *dValue2);

Description: This routine retrieved the determined resistance values from the instrument. This routine also performs averaging on the values, only after 5 measurements the value is valid.
The calling software is responsible for performing enough measurements

<i>Input:</i>	-	
<i>Output:</i>	*dValue1	resistance value for Channel 1
	*dValue2	resistance value for Channel 2
	returnvalue	E_NO_ERRORS
		E_NOT_INITIALIZED
		E_NOT_SUPPORTED
		E_NO_HARDWARE

If you have any suggestions and/or remarks concerning the DLL's or the manual, please contact:

TiePie engineering
PO Box 290
8600 AG SNEEK

Visitors address:

TiePie engineering
Koperslagersstraat 37
8601 WL SNEEK
Tel.: +31 515 415 416
Fax: +31 515 418 819

